



Specifying a user's ho

Configuring the Server

Configuring the server as a Windows se

6. Select

To administer a remote server

1. On the remote computer, start the Administrator Interface.
2. In the left pane, expand the Server's group and select the server.

Rotating server logs

19. Select the **Create standard subfolders...** check box to automatically cr

- €# Disabling an account after a defined number of incorrect password attempts
- €# Enabling time out

To disable an

Controlling a

5. At the bottom of the right pane, click **Refres**

€# 0

The following i

This means tha

2. In the left window, select the top level folder that has the permissions you want for its subfolders.
3. Right-click the folder and choose **Reset Subfolders**.

the top level EMC /P <</MCID 2 >>BDC 6143 683.27986 Tm6a33398 Tm(.)TJET14 th399 /P <</

To map to a network drive in a workgroup

1. Install server. p

Warning: The user name and password you are currently logged on with will be passed to the Services Applet on the remote computer. You must have administrat

Commands tab

1. On

Using SSL and TLS

About SSL

SecusT/6 cket Layer (

Creating certificates

16. **Add this certi**

10. Return the certificate file (.crt) to the user.

5. Click the **Connection Options** tab.
6. Select **Enable FTP access** if you want to allow both standard FTP connections as well as SSL connections.

Disable SSL Connections

You can disable SSL support for every user o

44

€# You can follow the same process and require a public

Trigger event

if Comment

€#

ODBC

Using an ODBC data source for user authentication


GlobalSCAPE Secure FTP Server allows you to use an

Files/Folders do not show the date and time modified, only the ye

Uploads to the server from problematic connections

Forgo

8. Make a new site (or sites) using the filenames from the aud files. For example if the aud file is called "MyServer.aud" you need to make a site called "MySer



```
MsgBox "Compression and Encryption Failed, Exiting!"  
End If
```


To Change the MSIE FTP Client Mode

Internet Explorer warning

When you first install and start GlobalSCAPE Secure FTP Serv

Index

3des

| | |
|---------------------------|----|
| Create server group | 9 |
| Creating | 35 |
| Custom | 45 |
| Custom co | |

Start service